

MICROPATH PDF PRINTER

The Micropath PDF Printer can **ONLY** be activated / used from within Micropath applications that support PDF printing, i.e., the PDF drivers are embedded into the application.

Pathanal V4 running on a Windows 7 64-bit OS may experience a program "hangup" and/or defective PDF file creation.

Listed below are steps to manually configure the Micropath PDF printer for Windows 7 32-bit / 64-bit PDF printing. In summary, you will set the Micropath PDF printer to use port "nul" instead of LPT1 printer port. If the "nul" printer port **DOES NOT EXIST**, you will have to create this port as outlined in the steps below. If the "nul" port **DOES** exist, skip or omit steps 4 (Add Port), 5 and 6.

Steps To Manually Configure the Micropath PDF Printer Port

- 1) Make sure you are logged in as a user with administrator rights.
- 2) Select Control Panel, and click Printers.
- 3) Right-click the Micropath PDF Printer icon and select Run as administrator and Properties.
- 4) Select the Ports tab, then click the Add Port... button.
- 5) Select Local Port and click the New Port... button.
- 6) Enter NUL: for the new port name and click OK. Close the Printer Ports window.
- 7) Ensure that the NUL: port is selected in the Ports list.
- 8) Select the Advanced tab.
- 9) Select the Spool print documents radio button to make the options below it clickable.
- 10) Clear (uncheck) the box labeled Enable advanced printing features.
- 11) Select the Print directly to printer radio button again.
- 12) Click the Apply button, and then click OK.

Control Panel





